### J1a SwapForth Reference

James Bowman
jamesb@excamera.com
Excamera Labs
Pescadero
California USA

### © 2015, James Bowman All rights reserved

#### ANS Forth Compliance Label

J1a SwapForth is an ANS Forth System

Providing names from the  ${\bf Core}~{\bf Extensions}$  word set

# Contents

1.	Getting started	5
2.	Available Words  2.1. ANS Core Words	<b>7</b> 7
3.	The SwapForth Shell 3.1. Command reference	
4.	4.1. RAM Types	<b>11</b> 11 11
5.	5.1. Port Map.         5.1.1. \$0001: Pmod data         5.1.2. \$0002: Pmod direction         5.1.3. \$0008: PIO output         5.1.4. \$0004: LEDs	13 14 14 14 14 14
	5.1.6. \$2000: IrDA, flash and UART inputs	15

4 CONTENTS

# Getting started



Connect to the SwapForth board using a terminal program of your choice. Set the serial parameters to:

- 115200 baud
- 8 data bits, no parity, no stop bit (often called "8N1", and often the default)

swapForth v0.1

# Available Words

#### 2.1 ANS Core Words

J1a Swap Forth implements most, but not all, of the core ANS 94 Forth standard.

#### 2.2 Additional Words

# The SwapForth Shell

- 3.1 Command reference
- 3.2 Notes on Tethered Mode

# Memory

#### 4.1 RAM Types

The J1a implementation uses 8Kbytes of RAM in a split configuration.

The lower 4K is for code. This RAM is writable, and executable, but not (directly) readable. The variable CP (code pointer) points into this area. To read from this region, use the special word code@.

The upper 4K is for data. This RAM is writable and readable. The dictionary and all variables are located in this section. The variable DP points into this area.

#### 4.2 Dictionary Layout

The SwapForth dictionary is a linked list; the variable forth holds the start of this list. Each dictionary entry contains:

- next pointer address of the next dictionary entry, or zero for the last dictionary entry
- imm immediate bit
- count length of the name, in characters, 1-31
- $name_1$   $name_n$  characters in name. If the length of the name is even, then a padding byte is appended
- $\bullet$  **xt** execution token for the word

15	14	13	12	11	10	9	8	7	6	5	4	3	2	1	0	
	next pointer i															
			nar	$\mathrm{ne}_1$						coı	ınt					
$\mathrm{name}_n$									$name_{n-1}$							
xt																

# iCEstick Hardware interface



The J1a for iCEstick includes connections to the iCEstick peripherals:

- SPI flash
- LEDs
- IrDA tranceiver
- Pmod connector
- prototyping connectors
- UART

Access to peripherals is via the io@ and io! words. Peripherals are port-mapped into a 16-bit IO address space.

Most ports are either read-only or write-only. For read-only ports, writing to the port has no effect. For write-only ports, reading from the port gives zero.

As an example of direct port access, this word blinks the on-board LEDs when a signal on IrDA is detected.

```
: x
begin
  $2000 io@ \ read from input port
  8 and 0= \ true if bit 3 (IrDA RXD) is 0
  $0004 io! \ write to LEDS
  again
;
```

#### 5.1 Port Map

#### 5.1.1 \$0001: Pmod data

Not yet implemented.

#### 5.1.2 \$0002: Pmod direction

Not yet implemented.

#### 5.1.3 \$0008: PIO output

Write-only port \$0008 controls the flash and IrDA outputs.



#### 5.1.4 \$0004: LEDs

The five on-board LEDS are controlled by write-only port at address \$0004. Setting a bit to 1 lights the corresponding LED.



5.1. PORT MAP 15

#### 5.1.5 \$1000: UART data

#### 5.1.6 \$2000: IrDA, flash and UART inputs

Read-only port 2000 contains the input signals from the IrDA receiver, SPI flash, and UART.

1	15	14	13	12	11	10	9	8	7	6	5	4	3	2	1	0
													IrDA RXD	flash MISO		UART busy